

# **Licensing Toolkit User's Guide**

**Version 9.5.3**



Printed: December 2011

The information contained in this document is subject to change without notice and should not be construed as a commitment by Synergex. Synergex assumes no responsibility for any errors that may appear in this document.

The software described in this document is the proprietary property of Synergex and is protected by copyright and trade secret. It is furnished only under license. This manual and the described software may be used only in accordance with the terms and conditions of said license. Use of the described software without proper licensing is illegal and subject to prosecution.

© Copyright 1992, 1993, 1997, 2001–2003, 2005, 2007–2011 by Synergex

Synergex, Synergy, Synergy/DE, and all Synergy/DE product names are trademarks or registered trademarks of Synergex.

Windows is a registered trademark of Microsoft Corporation.

All other product and company names mentioned in this document are trademarks of their respective holders.

DCN LK-01-9502

Synergex  
2330 Gold Meadow Way  
Gold River, CA 95670 USA

<http://www.synergex.com>

phone 916.635.7300

fax 916.635.6549

# Contents

## Licensing Toolkit

Welcome to Licensing Toolkit	2
Additional resources	2
Securing Synergy Applications with License Manager	3
LM_INFO – Return license information about the system	4
LM_LOGIN – Log in and return a unique token and configuration information	5
LM_LOGOUT – Log out a previously logged in license	8
Securing xNetLink Applications with License Manager	10
win_lm_login – Log in and return a unique token	12
win_lm_logout – Log out a previously logged in license	14
Generating Configuration Keys	16
License Key Generator Utility	17
Checking License Usage	19
win_lm_stat – Return current license usage	20
Error Messages	21

## Glossary

# Licensing Toolkit

## **Welcome to Licensing Toolkit 2**

Provides general information about Licensing Toolkit and lists additional sources of information.

## **Securing Synergy Applications with License Manager 3**

Describes how to secure your Synergy applications with License Manager. Includes syntax for the LM\_INFO, LM\_LOGIN, and LM\_LOGOUT subroutines.

## **Securing xfNetLink Applications with License Manager 10**

Describes how to secure your xfNetLink applications with License Manager. Includes syntax for the win\_lm\_login and win\_lm\_logout functions.

## **Generating Configuration Keys 16**

Describes how to generate configuration keys for your customers. Includes syntax for the License Key Generator Utility.

## **Checking License Usage 19**

Describes how to obtain the current licence usage for an application. Includes syntax for the win\_lm\_stat function.

## **Error Messages 21**

Lists the errors that could occur when using the Licensing Toolkit API.

# Welcome to Licensing Toolkit

Synergy/DE™ Licensing Toolkit consists of the Licensing Toolkit API and the License Key Generator utility:

- ▶ The Licensing Toolkit API, which is distributed with Core Components, enables you to build Synergy/DE License Manager protection into your own Synergy and *x/NetLink* applications. The API includes both Synergy routines and a C API, **syncli\_api.dll**, which contains three functions that can be called from a C, C++, .NET, or any other application that can call a DLL.
- ▶ The License Key Generator utility is used to generate configuration keys for your customers so that they may use your application. This utility is sent to you by Synergex® upon request. At the same time, Synergex will assign a producer code to your company, which you will need when using the Licensing Toolkit API.

This document explains how to use Licensing Toolkit to secure your applications with License Manager. When a Synergy application has been secured with License Manager, the application will not run unless License Manager is installed and configured to recognize it. You can configure an application to allow a maximum number of concurrent users, to secure specific components, and to run for a limited amount of time.

Licensing Toolkit can also be used to implement a reporting routine that can be used to satisfy license usage requirements for *x/ServerPlus* applications, as described in the Synergex Synergy/DE Product License Agreement Terms and Conditions (PLA). See your Synergy/DE account manager for details on the reporting requirements.

## Additional resources

- ▶ The “[Configuring License Manager](#)” chapter of the *Installation Configuration Guide* for information about License Manager, configuration keys, and Synergy Key files.
- ▶ **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site. In addition to **lmtx.exe**, an interactive interface to the License Key Generator, this file includes other routines that illustrate the use of Licensing Toolkit. See the **readme** file included in the download for details.
- ▶ **LicensingToolkitExample.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site. This file contains examples of how to create license keys, install license keys onto runtime systems, and implement license checking in your applications. It includes both Workbench and Visual Studio projects; the latter demonstrates using the Licensing Toolkit API from a C# application. See the **readme** file included in the download for details.

If you cannot find the information you need in this manual or in the resources listed above, you can contact Synergy/DE Developer Support department at 800.366.3472 (in the U.S. and Canada), 0800.898368 (in the U.K.), or 916.635.7300 (in all other locations). To learn about your Developer Support options, contact your Synergy/DE account manager at one of the above numbers.

# Securing Synergy Applications with License Manager

Follow these steps to secure a Synergy application with License Manager.

1. Install the License Key Generator utility on a Windows machine and then install the configuration key you received from Synergex.
2. Create an application code for each application you want to secure with License Manager.

The application code is passed when you make calls to LM\_LOGIN and LM\_LOGOUT. It is also used when you generate configuration keys. The application code can have a maximum of six alphanumeric characters.
3. Include a call to the LM\_LOGIN subroutine at the beginning of the application you want to secure.

LM\_LOGIN calls License Manager and returns a status value and configuration information about the log-in. See [page 5](#) for more information.
4. Include a call to the LM\_LOGOUT subroutine at all exit points in your application.

LM\_LOGOUT frees the current user process from the tally of concurrent log-ins for the application and returns a status. See [page 8](#) for more information.
5. Write a subroutine to handle your security, including any forced exit resulting from a security failure. Although LM\_LOGIN and LM\_LOGOUT return status values, these values do not affect your application. Your security subroutine must include code to handle the returned status.



You can use the .NODEBUG compiler directive to prevent debugging of this subroutine. The .NODEBUG directive deactivates debugging for modules that you don't want anyone to look at. You can place it anywhere in your subroutine. For more information, see [.NODEBUG](#) in the "Preprocessor and Compiler Directives" chapter of the *Synergy Language Reference Manual*.

---

6. (Recommended) Add an application-level TRY-CATCH-FINALLY statement to your main application module to ensure that the license is logged out if an untrapped error occurs.
7. (Recommended for Windows) Add code to log errors to the Windows event log.
8. After your application is installed at a customer site, request that the customer send you the licensee name and registration string.
9. Generate configuration keys for your customers, using the licensee names and registration strings they send you. See ["Generating Configuration Keys" on page 16](#).
10. Send the configuration keys to your customers so that they can configure License Manager to run your applications.

## LM\_INFO – Return license information about the system



```
xcall lm_info(lm_stat, lm_site)
```

### Arguments

*lm\_stat*

Returned with the License Manager site status. This will be 0 (success) or one of the codes listed in the table on [page 21](#). (n)

*lm\_site*

Returned with the site information record: (a)

	,a6	Blanks
lm_licensee	,a50	Licensee name entered during registration
lm_regstr	,a12	Registration string
lm_regdat	,d8	Registration date (YYYYMMDD)
lm_timeout	,d8	Pre-install time-out date (YYYYMMDD)

### Discussion

The LM\_INFO subroutine returns License Manager information about the system on which your application is running. The default pre-install time-out date is 14 days after the registration date.

The status value returned in *lm\_stat* is for checking success or providing an application-related license error message. This value has no effect on your application; you must write code to handle the returned status.

You can access system error codes with %SYSERR, which may assist in troubleshooting.

### Examples

```
xcall lm_info(myStat, mySiteInfo)
```

See also **lm\_auth.dbl** in **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

## LM\_LOGIN – Log in and return a unique token and configuration information

WT	WN	U	
----	----	---	--

```
xcall lm_login(app_stat, producer, application, token, [lm_record], [slot_num], [check]
&
[, seat])
```

### Arguments

#### *app\_stat*

Returned with the log-in status. The most common ones are listed below; see the table on [page 21](#) for additional codes that could be returned. **(n)**

- 0 Product has been configured or a license is available.
- 1 Product has not been configured.
- 2 Concurrent user maximum reached.
- 7 Product demo has expired.

#### *producer*

The producer code for your company. (This code was assigned to your company by Synergex when you requested the License Key Generator.) **(a)**

#### *application*

The code that you created to refer to the application. It can be up to six characters long. **(a)**

#### *token*

Returned with the log-in token, which is a key that is maintained in License Manager. **(i4)**

#### *lm\_record*

(optional) Returned with the information that was specified when the application was configured with License Manager: **(a)**

```
lm_applic ,a6      ;Application code
lm_usrmax ,d4      ;Maximum number of concurrent users
lm_expdat ,d8      ;Time-out date (YYYYMMDD)
lm_insdatt ,d8      ;Installation date (YYYYMMDD)
lm_custom ,a100    ;Developer-defined information
```

#### *slot\_num*

(optional) Returned with the slot number, which ranges from 1 to the number of users for which the product is configured. Slots are used as they become available; consequently, the slot number will not necessarily tell you the current number of users. **(n)**

*check*

(optional) One of the following options:

- 0** Log in the license. (default)
- 1** Check whether the license is available.
- 2** Check whether the license is configured.

Passing anything other than 0, 1, or 2 is the same as passing 1. When *check* is 1 or 2, License Manager does not request a log-in slot, and the concurrent number of users is not incremented. **(n)**

*seat*

(optional) A 32-bit integer set to 0 (zero) or the value designated to represent the seat. **(i)**

## Discussion

The LM\_LOGIN subroutine requests a log-in “slot” from License Manager for the specified application or performs a license check (when *check* is non-zero), and then returns configuration information about the log-in.



For security reasons, we recommend that you encode the strings for producer code and application code in your routines.

---

When *check* is 0 (or not passed), the call to LM\_LOGIN returns a token if the license is configured. This token should be saved by your application and used in the call to LM\_LOGOUT. License Manager will only recognize log-outs with a matching token. You need to retain the token only while the license is logged in, as a token has meaning only for the log-in for which it was obtained.

When *check* is 0 (or not passed) or 1 and the license is unconfigured but within the 14-day demo period, LM\_LOGIN returns a status of 0 (success) and a token of 0. In this case, a log-out is not required, since no log-in slot has been taken.

When using the *seat* argument, the value you should pass depends on the type of application:

- ▶ For a stand-alone application, where the user is running the application interactively from the same workstation that the user is logged in to, pass 0 for *seat* or just don't pass *seat* at all. (All licenses logged in and out are based on the workstation being the seat.)
- ▶ In a server environment, where there are multiple processes running on the same machine (such as an *x/NetLink-x/ServerPlus* application), you will need to decide how a “seat” should be represented within your application. *Seat* can be any 32-bit integer. The seat should be unique among seats, but the same for each instance of a particular seat. For example, you may want to use the client's IP address. Each license taken by the same seat for the same product code will be shared. In a server environment, you must include the seat to log out the correct license.

The status value returned by LM\_LOGIN in *app\_stat* is for checking success or providing application-related license error messages. This value has no effect on your application; you must write code to handle the returned status. For example, if LM\_LOGIN returns 2 (concurrent user maximum reached), you could deny the user access to your application and present an error message stating the problem. You can access system error codes with %SYSERR, which may assist in troubleshooting.

## Examples

See **lm\_auth.dbl** in **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

## LM\_LOGOUT – Log out a previously logged in license

WT	WN	U	
----	----	---	--

```
xcall lm_logout (lo_stat, producer, application, token[, seat])
```

### Arguments

*lo\_stat*

Returned with the log-out status. The most common ones are listed below; see the table on [page 21](#) for additional codes that could be returned. **(n)**

- 0 Success.
- 3 Invalid token.

*producer*

The producer code for your company. (This code was assigned to your company by Synergex when you requested the License Key Generator.) **(a)**

*application*

The code that you created to refer to the application. **(a)**

*token*

The token obtained from the LM\_LOGIN call (see [page 5](#)) and used here to log out. **(i4)**

*seat*

(optional) A 32-bit integer set to the value that was passed in the *seat* argument to the LM\_LOGIN call. **(i)**

### Discussion

LM\_LOGOUT is used only when you have called LM\_LOGIN with *check* set to 0 (or not passed) and the returned token was non-zero.

The LM\_LOGOUT subroutine doesn't log out a process in the usual sense (that is, it does not prevent the application from continuing); rather, it requests that License Manager release the "slot" for the specified license so that another user can log in and use the available slot.

If the token returned by the call to LM\_LOGIN is non-zero, it should be saved by your application and passed to LM\_LOGOUT. The token ensures that the process that is logging out is authorized to do so.

If you passed a non-zero value for *seat* in the call to LM\_LOGIN, pass the same value for *seat* in the call to LM\_LOGOUT. The seat, in combination with the token, ensures that the correct license is logged out in a server environment. If you pass *seat* with LM\_LOGIN and fail to pass the same *seat* value with LM\_LOGOUT, the results could be unpredictable.

On Windows, you must call LM\_LOGOUT as part of your exit procedure, or the license will stay in use until the license server logs it out; this could take as long as 20 minutes. You should also call LM\_LOGOUT in case of an application error.

On UNIX, although LM\_LOGOUT is not required (normally licenses are logged out automatically when the runtime process has terminated), we recommend that you call LM\_LOGOUT as part of your normal exit procedure, especially if your application STOP chains to another program. You should also call LM\_LOGOUT in case of an application error.

The status values returned by LM\_LOGOUT are for your information only; they have no effect on your application. You should write code to handle the returned status. You can access system error codes with %SYSERR, which may assist in troubleshooting.

# Securing xfNetLink Applications with License Manager

Follow these steps to secure xfNetLink .NET or xfNetLink COM applications with License Manager. (**Syncli\_api.dll** is not currently supported on xfNetLink Java.) These instructions presume you are using xfNetLink, but the functions in **syncli\_api.dll** can be called from a C, C++, .NET, or any other application that can call a DLL.

1. Install the License Key Generator utility on a Windows machine and then install the configuration key you received from Synergex.
2. Install xfNetLink, which includes **syncli\_api.dll**. This DLL contains the functions you will call from your client application to implement licensing.
3. Create an application code for each application you want to secure with License Manager.

The application code is passed when you make calls to `win_lm_login` and `win_lm_logout`. It is also used when you generate configuration keys. The application code can have a maximum of six alphanumeric characters.

4. Include a call to the `win_lm_login` function at the beginning of the application you want to secure.  
The `win_lm_login` function calls License Manager and returns a status value. See [page 12](#) for more information.
5. Include a call to the `win_lm_logout` function at all exit points in your application.  
The `win_lm_logout` function frees the current user process from the tally of concurrent log-ins for the application and returns a status. See [page 14](#) for more information.
6. Write a subroutine to handle your security, including any forced exit resulting from security failure. Although `win_lm_login` and `win_lm_logout` return status values, these values do not affect your application. Your security subroutine must include code to handle the returned status.
7. (Recommended) Add an application-level try-catch-finally statement to your code to ensure that the license is logged out when an untrapped error occurs.
8. (Recommended) Add code to log errors to the Windows event log.

## Deployment

This section describes what to do when you are ready to deploy your secured xfNetLink application at a customer site.

1. Set up a Synergy license server on a Windows machine at the customer site.
2. Install xfNetLink and your application on the client machine. This can be the same machine as the license server or it may be a different machine.
3. On the xfNetLink machine, run **lmutil.exe** (included in the xfNetLink installation) to initialize License Manager as a license client to your license server machine:

```
lmutil -cserver_name -nc
```

4. Run **lmu -b** on the license server machine to get the registration string.
5. Use the licensee name and registration string to generate configuration keys. See [“Generating Configuration Keys” on page 16](#).
6. Install the keys on the customer’s license server machine. This configures License Manager to run your application.

## win\_lm\_login – Log in and return a unique token



```
int WINAPI win_lm_login(char *producer, char *application, int check, int seat,
                        int *token, int *syserr)
```

### Arguments

#### *producer*

The producer code for your company. This is a null-terminated 8-bit ANSI string. (This code was assigned to your company by Synergex when you requested the License Key Generator.)

#### *application*

The code that you created to refer to the application. This is a null-terminated 8-bit ANSI string and can be up to six characters long.

#### *check*

An int32 set to one of the following values:

- 0**      Log in the license.
- 1**      Check whether the license is available.
- 2**      Check whether the license is configured.

Passing anything other than 0, 1, or 2 is the same as passing 1. When *check* is 1 or 2, License Manager does not request a log-in slot, and the concurrent number of users is not incremented.

#### *seat*

An int32 set to 0 (zero) or the value designated as representing the seat.

#### *token*

An int32 pointer returned with the log-in token, which is a key that is maintained in License Manager.

#### *syserr*

An int32 pointer returned with a system error code when the return status is other than 0.

### Discussion

The win\_lm\_login function requests a log-in “slot” from License Manager for the specified application or performs a license check (when *check* is non-zero).

When *check* is 0, win\_lm\_login returns a token if the license is configured. This token should be saved by your application and used in the call to win\_lm\_logout. License Manager will only recognize log-outs with a matching token. You need to retain the token only while the license is logged in, as a token has meaning only for the application log-in for which it was obtained.

When *check* is 0 or 1 and the license is unconfigured but within the 14-day demo period, win\_lm\_login returns a status of 0 (success) and a token of 0. In this case, a log-out is not required, since no log-in slot has been taken.

When using the *seat* argument, the value you should pass depends on the type of application:

- ▶ For a stand-alone application, where the user is running the application interactively from the same workstation that the user is logged in to, pass 0 for *seat*.
- ▶ In a server environment where there are multiple users (such as an *xfNetLink-xfServerPlus* application), you will need to decide how a “seat” should be represented within your application. *Seat* can be any 32-bit integer. The seat should be unique among seats, but the same for each instance of a particular seat. For example, you may want to use the client’s IP address. In a server environment, you must include the seat to log out the correct license.



Do not attempt to call the win\_lm\_login function from the load event of a DLL because a thread cannot be created within a load event.

---

The win\_lm\_login function returns a status value. The most common ones are listed below; see the table on [page 21](#) for additional codes that could be returned.

- 0 Success.
- 1 Product has not been configured.
- 2 Concurrent user maximum reached.
- 7 Product demo has expired.

These values are for checking success or providing application-related license error messages; they have no effect on your application. You must write code to handle the returned status. For example, if win\_lm\_login returns 2 (concurrent user maximum reached), you may want to deny the user access to your application and present an error message stating the problem.

## Examples

See **lmdltest.c** in **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

## win\_lm\_logout – Log out a previously logged in license



```
int WINAPI win_lm_logout(char *producer, char *application, int token,
                        int seat, int *syserr)
```

### Arguments

#### *producer*

The producer code for your company, provided by Synergex. This is a null-terminated 8-bit ANSI string. (This code was assigned to your company by Synergex when you requested the License Key Generator.)

#### *application*

The code that you created to refer to the application. This is a null-terminated 8-bit ANSI string and can be up to six characters long.

#### *token*

The token obtained from the win\_lm\_login call (see [page 12](#)) and used here to log out.

#### *seat*

An int32 set to the value that was passed in the *seat* argument to win\_lm\_login.

#### *syserr*

An int32 pointer returned with a system error code if the call fails.

### Discussion

The win\_lm\_logout function is used only when you have called win\_lm\_login with *check* set to 0 and the returned token was non-zero.

The win\_lm\_logout function doesn't log out a process in the usual sense (that is, it does not prevent the application from continuing). Instead it requests that License Manager release the "slot" for the specified license so that another user can log in and use the available slot.

If the token returned by the call to win\_lm\_login is non-zero, it should be saved by your application and passed to win\_lm\_logout. The token ensures that the process that is logging out is authorized to do so.

If you passed a non-zero value for *seat* in the call to win\_lm\_login, pass the same value for *seat* in the call to win\_lm\_logout. The seat, in combination with the token, ensures that the correct license is logged out in a server environment. If you pass *seat* with win\_lm\_login and fail to pass the same *seat* value with win\_lm\_logout, the results could be unpredictable.

You must call win\_lm\_logout as part of your exit procedure and on an exception, or the license will stay in use until the license server logs it out; this could take as long as 20 minutes.

The win\_lm\_logout function returns a status value. The most common ones are listed below; see the table on [page 21](#) for additional codes that could be returned.

0 Success.

3 Invalid token.

These status values are for your information only; they have no effect on your application. You must write code to handle the returned status.

## Examples

See **lmdltest.c** in **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

## Generating Configuration Keys

Once your customers have installed your application, you will need to request that they send you the registration string and licensee name. You must then generate configuration keys, which the customer will use to configure License Manager to run your application.

There are two ways to generate configuration keys:

- ▶ Run the License Key Generator utility, **lmk.exe**, from the command line. This method enables you to configure one product at a time. The configuration key is displayed on screen, or you can choose to put it in a Synergy Key file (**.skf**), which can be used by your customer to install the keys. See [page 17](#).
- ▶ Use the interactive interface to the License Key Generator, **lmkx**. The **lmkx** program simplifies the collection of information required to generate configuration keys, and enables you to generate keys for several applications at once for each licensee name. It also creates a Synergy Key file. You can download **lmkx** from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site. The CodeExchange download (**Licensing\_TK\_Examples.zip**) includes the source code for **lmkx** so that you can modify it as necessary to suit your needs.



The **lmkx** program is also useful for creating a demo license that times out, because it enables you to enter either a time-out date or a specific number of days.

---

## License Key Generator Utility

The License Key Generator utility, **lmk**, is used to generate configuration keys. As with other Synergy/DE products, you must configure License Manager to allow **lmk** to run, using the configuration key sent to you by Synergex. Once configured, it cannot be transferred to another machine. In addition, **lmk** is protected from accidentally being copied into a distribution to your customers. The **lmk** utility is available on Windows only.

### Syntax

`lmk [-option] [...]`

### Arguments

*option*

One or more of the following:

<b>aapp_code</b>	The application code that you created to represent the application.
<b>cname</b>	The licensee name (obtained from the customer site).
<b>d days</b>	The number of days since January 1, 1992 that you want the keys to be valid. If you don't want the product to time out, either don't use the <b>-d</b> option or set <i>days</i> to 0 (zero).
<b>fcfilename</b>	Create or overwrite a Synergy Key file named <i>filename</i> for a specified licensee. The <b>.skf</b> extension will be added if not specified.
<b>fafilename</b>	Append to an existing Synergy Key file named <i>filename</i> . The <b>.skf</b> extension will be added if not specified.
<b>h</b>	Display a help message that specifies the <b>lmk</b> syntax.
<b>rstring</b>	The registration string (obtained from the customer site).
<b>uusers</b>	The maximum number of users for <i>app_code</i> .
<b>v</b>	Display the version number of <b>lmk</b> .
<b>xstring</b>	An extended, developer-defined data string. This string can contain up to 100 characters.

### Discussion

Arguments that include spaces must be enclosed in quotation marks. For example, if you want to specify the licensee name ABC Consulting Corporation with the **-c** option, you'd enter it as

```
-c"ABC Consulting Corporation"
```

The **-d** option enables you to create a demo license that will expire after a specified number of days. It is easier to create a demo license using the **lmkx** program, because it allows you to enter either a time-out date or the number of days before time-out. The **lmkx** program is included in **Licensing\_TK\_Examples.zip**, which is available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

The **-x** option enables you to include your own string for anything that you want to check regarding the product that is being licensed. For example, you could use this string to check the version number of your application. (Note that you will have to include code in your application to handle the information included in the string.)

### Using Synergy Key files

The key file enables users to install keys without having to type the configuration key. If you don't specify the **-fc** option, the keys will display to the screen.

If you create a Synergy Key file with the **-fc** option, the file will be created in the current working directory unless you specify a complete path. You can also use a logical to specify the file location.

To put the keys in a Synergy Key file,

1. First, create the file with the **-c** and **-fc** options. For example,

```
lmk -cMickey -fcKEYS:Mickey
```

creates a file named **Mickey.skf** for licensee Mickey and places it in the directory specified by the **KEYS** logical. The file header will include the licensee name and the creation date.

2. Once the file is created, run **lmk** for each application code, and specify the key file with the **-fa** option. This will generate the keys and place them in the file. For example, to generate 10-user licenses for the application codes **CON5** and **MAR5** and place them in the **Mickey.skf** file, you would use the following:

```
lmk -acon5 -cMickey -r2580RCK7QG88 -u10 -faKEYS:Mickey
lmk -amar5 -cMickey -r2580RCK7QG88 -u10 -faKEYS:Mickey
```

For more information about key files, see the “[Configuring License Manager](#)” chapter of the *Installation Configuration Guide*.

## Checking License Usage

The `win_lm_stat` function (in **syncli\_api.dll**) returns the current license usage for an application that has been secured with the Licensing Toolkit API.

If you have an *xfNetLink* .NET or *xfNetLink* COM application, you can use the value returned by `win_lm_stat` to create a report of license usage, which can then be used to satisfy license usage requirements for *xfServerPlus* applications, as described in the PLA. Contact your Synergy/DE account manager for details on license usage requirements.

1. Secure the application using the routines in the Licensing Toolkit API. See [“Securing xfNetLink Applications with License Manager”](#) on page 10.
2. Write a routine to retrieve the license usage value from `win_lm_stat`. This function returns the current license usage for the specified application. (See [page 20](#).) We recommend that you write a separate utility to do this.
3. Gather the license usage information into a report.



You can use the `win_lm_stat` function to check license usage for any application that has been secured using the routines in the Licensing Toolkit API. When checking license usage in a Synergy application, use the Synergy DLL API with the `DLL_TYPE_WINAPI` convention to call `win_lm_stat`. See the [“Synergy DLL API”](#) chapter of the *Synergy Language Reference Manual* for information.

---

## win\_lm\_stat – Return current license usage

WT	WN		
----	----	--	--

```
int WINAPI win_lm_stat(char *producer, char *application, int *usage,
                      int *syserr)
```

### Arguments

#### *producer*

The producer code for your company, provided by Synergex. This is a null-terminated 8-bit ANSI string. (This code was assigned to your company by Synergex when you requested the License Key Generator.)

#### *application*

The code that you created to refer to the application. This is a null-terminated 8-bit ANSI string and can be up to six characters long.

#### *usage*

An int32 pointer returned with the current number of users.

#### *syserr*

An int32 pointer returned with a system error code if the call fails.

### Discussion

The *usage* argument returns the current license usage for the specified application code. This value can be used to prepare a report of license usage, as required for x/ServerPlus customers by the PLA.

The *win\_lm\_stat* function returns a status value. The most common ones are listed below; see the table on [page 21](#) for additional codes that could be returned.

- 0 Success.
- 1 Product has not been configured.

These status values are for your information only; they have no effect on your application. You must write code to handle the returned status.

If the call fails, *syserr* may be loaded with a system error number.

When calling *win\_lm\_stat* from a Synergy application, use the Synergy DLL API with the `DLL_TYPE_WINAPI` convention; see the “[Synergy DLL API](#)” chapter of the *Synergy Language Reference Manual* for information

### Examples

See **lmstattest.c** in **Licensing\_TK\_Examples.zip**, available from [Synergy CodeExchange](#) in the Resource Center on the Synergex web site.

# Error Messages

The table below shows errors that could occur when using the Licensing Toolkit API.

Number	Meaning	Comments
1	License not configured.	
2	Exceeded concurrent user maximum.	
3	Bad logout token.	
5	Unexpected failure in UNIX license server.	
6	License Manager internal consistency failure.	Run <b>Imu -k</b> . See “ <a href="#">The Imu utility</a> ” in the “Configuring License Manager” chapter of the <i>Installation Configuration Guide</i> .
7	Demo period has expired.	
171	Cannot access license file (or Windows registry).	
172	License Manager communications error (msgsnd/msggrsv). Likely configuration problem.	UNIX only
173	License Manager communications error (msgsnd/msggrsv). Likely configuration problem.	UNIX only
174	License Manager communications time-out.	Windows only
175	Cannot access license file (or Windows registry).	
176	Cannot access network license server.	Windows only
177	Old License Manager version is installed.	Install the latest License Manager.
179	Network license server is busy.	Windows only
180	License Manager internal consistency failure.	Run <b>Imu -k</b> . See “ <a href="#">The Imu utility</a> ” in the “Configuring License Manager” chapter of the <i>Installation Configuration Guide</i> .
181	License Manager communications error (msgsnd/msggrsv). Likely configuration problem.	UNIX only
182	License Manager communications error (msgsnd/msggrsv). Likely configuration problem.	UNIX only

Number	Meaning	Comments
183	Cannot access License Manager server (not running or MSGWAIT time-out).	UNIX only
184	License Manager internal consistency failure.	Run <b>Imu -k</b> . See <a href="#">“The Imu utility”</a> in the “Configuring License Manager” chapter of the <i>Installation Configuration Guide</i> .
185	Cannot access network license server.	Windows only
186	Exceeded concurrent user maximum.	
188	Network license server is busy.	Windows only

# Glossary

<b>application code</b>	A string of characters that you create and use to identify your application. The application code may have a maximum of six alphanumeric characters. Each application that you want to secure with License Manager must have its own application code.
<b>configuration key</b>	A string of characters generated by the License Key Generator utility based on a registration string provided by your customer. Your customer needs this key to configure License Manager to allow your products to run.
<b>key file</b>	Refers to a Synergy Key file ( <b>.skf</b> ), which is a file that contains configuration keys for one or more licensees. You can use a Synergy key file to automatically configure all products for a workstation at once.
<b>PLA</b>	Product License Agreement. Refers to the Synergex Synergy/DE Product License Agreement Terms and Conditions.
<b>producer code</b>	A number given to you by Synergex that identifies your company. This code is used by LM_LOGIN, LM_LOGOUT, win_lm_login, win_lm_logout, and win_lm_stat.
<b>registration string</b>	A string of characters generated by License Manager. Your customers must send you this string before you can generate configuration keys for them.
<b>skf</b>	Synergy key file. See <a href="#">key file</a> .
<b>slot</b>	A slot is allocated by License Manager each time someone starts the application. When you configure a product for a certain number of users, that number of slots is reserved.
<b>token</b>	A key that is maintained in License Manager to keep track of the licenses that are logged in. The token is obtained from the log-in process and used when logging out to ensure that the process that is logging out is authorized to do so.