

Instellingen "Sponsorslider op onze website"

Bekijk ook de video "[Sponsorslider op onze website](#)" op het Youtube kanaal "Sportlink Services"

Gebruikte instellingen voor een sponsorslider over de volle breedte van je website met een hoogte van 90px.



Settings – Global

Global		225
Carousel		x
Navigation	Dimensions:	90
Bullets		px
Filmstrip		Maximum width and height for slider.
Timer bar	Full width:	<input checked="" type="radio"/> Yes <input type="radio"/> No
Watermark		2.5
CSS		Ratio
Slider Callbacks		The image will stretch to the page width, taking the height based on dimensions ratio.
	Background fit:	<input checked="" type="radio"/> Cover <input type="radio"/> Fill <input type="radio"/> Contain
	Smart Crop	<input type="radio"/> Yes <input checked="" type="radio"/> No
	Fixed background:	<input type="radio"/> Yes <input checked="" type="radio"/> No
	Align:	Center
		Set the alignment of the slider.
	Effect:	Random
		Select the effect which will be applied when shifting from one slider to another.
	Effect duration:	800
		ms
		Define the time for the effect.
	Parallax Effect:	<input type="radio"/> Yes <input checked="" type="radio"/> No
		The direction of the movement, as well as the layer moving pace depend on the z-index value.

The direction of the movement, as well as the layer moving pace depend on the z-index value.

Global

- Carousel
- Navigation
- Bullets
- Filmstrip
- Timer bar
- Watermark
- CSS
- Slider Callbacks

Autoplay: Yes No
Choose whether to autoplay the sliders or not.

Enable loop: Yes No

Time Interval:
sec.
Set the time interval for the change of the sliders when autoplay is on.

Stop on hover: Yes No
The option works when autoplay is on.

Shuffle: Yes No
Choose whether to have the slides change in a random manner or to keep the original sequence.

Start with slide:
The slider will start with the specified slide. You can use the value 0 for random.

Music: Yes No
Choose whether to have music/audio track playback with the slider or not.

Smart Load: Yes No
Choose to have faster load for the first few images and process the rest meanwhile.

Background color:

%
Transparency value must be between 0 to 100.

Global

- Carousel
- Navigation
- Bullets
- Filmstrip
- Timer bar
- Watermark
- CSS
- Slider Callbacks

Border: PX

Set the border width, type and the color.

Border radius:
Use CSS type values.

Margin:
px
Set a margin for the slider.

Shadow:
Use CSS type values (e.g. 10px 10px 5px #888888).

Right click protection: Yes No
Disable image right click possibility.

Layer out on next: Yes No
Choose whether to have the layer effect out regardless of the timing between the hit to the next slider or skip the effect out.

Turn SliderWD Media Upload: Yes No
Choose the option to use the custom media upload instead of the WordPress default for adding images.

Add font-family:
 Add to Google fonts
The added font family will appear in the drop-down list of fonts.

Published: Yes No
Choose whether to publish the mentioned slider or not.

Settings – Carousel

Global	
Carousel	Carousel: <input checked="" type="radio"/> Yes <input type="radio"/> No If you activate this feature the effects you had chosen in Global settings for your slider will not play.
Navigation	
Bullets	
Filmstrip	
Timer bar	
Watermark	
CSS	
Slider Callbacks	
	Number of images for carousel: <input type="text" value="16"/> Afhankelijk van het aantal sponsorlogo's
	Carousel image ratio: <input type="text" value="0.85"/> The value must be between 0 and 1.
	Container fit: <input checked="" type="radio"/> Yes <input type="radio"/> No
	Fixed width: <input type="text" value="900"/> px
	Background image angle: <input type="text" value="0"/> deg
	Background image grayscale: <input type="text" value="0"/> % You can change the color scheme for background images to grayscale. Values must be between 0 to 100
	Background image transparency: <input type="text" value="0"/> % You can set transparency level for background images. Values should be between 0 to 100

Settings – Navigation

Global	
Carousel	
Navigation	
Bullets	
Filmstrip	
Timer bar	
Watermark	
CSS	
Slider Callbacks	

Next / Previous buttons: Yes No
Choose whether to display Previous and Next buttons or not.

Mouse swipe navigation: Yes No

Touch swipe navigation: Yes No

Mouse wheel navigation: Yes No

Keyboard navigation: Yes No

Show Navigation buttons: On hover Always


Image for Next / Previous buttons: Default Custom Styled
Choose whether to use default navigation buttons or to upload custom ones.

Next / Previous buttons style: Angle
Choose the style of the button you prefer to have as navigation buttons.

Next / Previous buttons size:
px
Set the size for the next / previous buttons.

Play / Pause button: Yes No
Choose whether to display Play and Pause buttons or not.

Image for Play / Pause buttons: Default Custom Styled
Choose whether to use default play/pause buttons or to upload custom ones.

Play / Pause buttons style: 

Global	
Carousel	
Navigation	
Bullets	
Filmstrip	
Timer bar	
Watermark	
CSS	
Slider Callbacks	

Play / Pause button size:
px
Set the size for the play / pause buttons.

Buttons color:
Select a color for the navigation buttons.

Hover color:
Select a hover color for the navigation buttons.

Border:
px

Select the type, size and the color of border for the navigation buttons.

Border radius:
Use CSS type values.

Background color:

%
Transparency value must be between 0 to 100.

Settings – Bullets

Global	Enable bullets:	<input type="radio"/> Yes <input checked="" type="radio"/> No Choose whether to have navigation bullets or not.
Carousel	Show bullets:	<input type="radio"/> On hover <input checked="" type="radio"/> Always Select between the option of always displaying the bullets or only when hovered.
Navigation	Show thumbnail on bullet hover:	<input type="radio"/> Yes <input checked="" type="radio"/> No
Bullets	Position:	Top Select the position for the navigation bullets.
Filmstrip	Bullets type:	<input type="radio"/> Default <input type="radio"/> Custom <input checked="" type="radio"/> Styled <input type="radio"/> Text
Timer bar	Bullet style:	Square O <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> Choose the style for the bullets.
Watermark	Size:	20 px Define the size of the navigation bullets.
CSS	Color:	FFFFFF Select the color for the navigation bullets.
Slider Callbacks	Active color:	FFFFFF Select the color for the bullet, which is currently displaying a corresponding image.
	Margin:	3

Settings – Filmstrip

Global	Enable filmstrip:	<input type="radio"/> Yes <input checked="" type="radio"/> No Choose whether to have thumbnails of the slides displayed as a filmstrip or not.
Carousel	Position:	Top Set the position of the filmstrip.
Navigation	Thumbnail dimensions:	100 x 50 px Define the maximum width and height of the filmstrip thumbnails.
Bullets	Background color:	000000 Select the background color for the filmstrip.
Filmstrip	Thumbnail separator:	0 px Set the separator for the thumbnails.
Timer bar	Active border:	0 px None FFFFFF The thumbnail for the currently displayed image will have a border. You can set its size, type and color.
Watermark	Deactive transparency:	50
CSS		
Slider Callbacks		

Settings – Time Bar

Global

Carousel

Navigation

Bullets

Filmstrip

Timer bar

Watermark

CSS

Slider Callbacks

Enable timer bar: Yes No
You can add a bar displaying the timing left to switching to the next slide on autoplay.

Type:
Choose the type of the timer bar to be used within the slider.

Size:
px
Define the height of the timer bar.

Color:
100
%
Transparency value must be between 0 to 100.

Settings – Watermark

Global

Carousel

Navigation

Bullets

Filmstrip

Timer bar

Watermark

CSS

Slider Callbacks

Please note that the **Fill** and **Contain** options will work fine with **Watermark** option regardless of the image dimensions, whereas you need to **resize the image and upload it again**.

Watermark type: None Text Image
Choose what kind of watermark you want to use.

Settings – CSS

Global

Carousel

Navigation

Bullets

Filmstrip

Timer bar

Watermark

CSS

Slider Callbacks

Css:

Add custom CSS to apply custom changes to the slider.

Settings – Slider Callback

Global

Carousel

Navigation

Bullets

Filmstrip

Timer bar

Watermark

CSS

Slider Callbacks

Add new callback:

On slider Init

+