I'm not robot
reCAPTCHA
Continue

Intel amt management

Filter by Show More No more matches Intel Active Management (AMT) technology is a hardware-based technology built into computers with Intel vPro technology. AMT is designed to help system administrators remotely manage and protect out-of-band computers when PC power is turned off, the operating system (OS) is unavailable (hanging, locked, corrupted, missing), software management agents are missing, or hardware (such as a hard drive or memory drive) has failed. [4] Intel AMT versions are integrated into a small secondary processor located on the motherboard. This OOB driver has built-in firmware running on the manage capacity engine (ME), a small stand-alone processor built into the northbridge (or network card for AMT 1.0) on the motherboard. The AMT firmware is stored in the same SPI flash memory component used to store the BIOS and is usually updated along with the BIOS. FWH (Firmware Hub) or LPC firmware storage does not support AMT. [2] In general, an AMT version can be upgraded in the software to the next minor version. New major versions of Intel AMT are integrated into a new chipset and updated through new hardware. Intel AMT 1.0 — Intel platforms based on the Intel 82573E controller (Tekoa; typically 945, ICH7) Gigabit Ethernet, for example, the Intel D975XBX2 motherboard. This release provides basic NVRAM, hardware asset, event logging, and other basic features. Does not provide Intel System Defense network filters. Intel AMT 2.0 (2007) — Intel vPro desktop platforms based on Intel Q963/Q965 chipsets (Broadwater-Q, ICH8), for example, the Intel DQ965GF motherboard. [6] Intel AMT 2.1 — Intel AMT 2.0 + AMT (Intel Management Engine Wake on LAN) power savings and bug fixes (compatible with the same platforms as Intel AMT 2.0). [6] Intel AMT 2.2 — Intel AMT 2.1 + Remote Setup and bug fixes (compatible with the same platforms as Intel AMT 2.1 and Intel AMT 2.0). [6] Intel AMT 2.5 — Intel Centrino Pro mobile platforms based on GM965/PM965 chipsets (Santa Rosa: Crestline, ICH8M). [6] Intel AMT 2.6 — Intel AMT 2.5 + Remote Configuration and bug fixes (compatible with the same platforms as Intel AMT 2.5). [6] Intel AMT 3.0 — Intel vPro desktop platforms based on Intel Q35 chipsets (Weybridge: Bearlake-Q, ICH9), for example, the Intel DQ35MP motherboard. [4] Intel AMT 3.1 — Support for Intel AMT 3.0 + Linux (Red Hat and SUSE) (compatible with the same desktop platforms as Intel AMT 3.0; uses the same firmware). [7] Intel AMT 3.2 — Intel AMT 3.0 + DASH 1.0 Support Additional (Simplified Configuration) Bug fixes (compatible with the same desktop platforms as Intel AMT 3.1 and Intel AMT 3.0). [7] Intel AMT 4.0 — Mobile platforms with Intel Centrino 2 with vPro based on GM45 or 47/PM45 chipsets (Montevina: Cantiga, ICH9M). [8] Intel AMT 4.1 — Intel AMT 4.0 + Intel Anti-Theft Technology. Compatible with the same mobile platforms as Intel AMT 4.0, and based on GM45 chipset (Montevina, ICH9M). [9] [9] AMT 5.0 — Intel Core 2 vPro desktop platforms (released September 22, 2008) based on Intel Q45 chipsets (McCreary: Eaglelake-Q, ICH10). [10] Intel AMT 6.0 — Intel Core i5/7 vPro desktop platforms based on Q57 chipset (Piketon: Ibex Peak), Core i5/7 vPro based mobile platforms QM57 and QS57 chipset (Calpella: Ibex Peak) and Xeon 3400 series/Core i5 vPro input workstation platforms based on the 3450 chipset. Intel AMT 7.0 Chipset — Intel Q67 Chipset (Sugar Bay: Cougar Point), QM67 mobile chipset, and QS67 (Huron River: Cougar Point). Intel AMT 8.0 Chipset — Intel Q75 and Q77 chipset (Maho Bay: Panther Point), QM77 mobile chipset, and QS77 (Chief River: Panther Point). Intel AMT 9.0 — Intel Q87 Chipset, QM87 Mobile Chipset (Lynx Point). The SOAP(EOI) protocol has been removed. Intel AMT 10.0 — Intel Q97 Chipset, SoC only. Intel AMT 11.0 — Intel Q170, Q150, .232, CM236, C236 Chipsets. Intel AMT 11.5 — Intel Q270 Chipsets, CM238, CM248. Intel AMT 12.0 — Intel Q370 Chipset. [11] Intel AMT 14.0 — Intel Q470 Chipset. [12] Comparison of AMT Versions The following is a comparison of the various features supported by each version of Intel AMT[13][14] Feature AMT 1.0 (Desktop) AMT 2.0/2.1 (Desktop) AMT 2 .5/2.6 (Mobile) AMT 3.0 (Desktop) AMT 4.0 (Mobile) AMT 5.0 (Desktop) 6.0 (Desktop & Mobile) 7.0 and 8.0 (Desktop & Mobile) 9.0 (Desktop & Mobile) 10.0 (Desktop & Mobile) 11.0 (Desktop & Mobile) 12.0 (Desktop & Mobile) Hardware Yes Yes Yes