



1 Overview.....1

2 How to Setup Mapping on Metered Usage Level Field1

1 Overview

When using Configuration Packages to import Rental Prices, which include Metered Usage Pricing, then mapping is required on the table field Metered Usage Price Limits.

This is due to the Rental Price card table field, Metered Usage Price Limits, and the available options in the picklist having had the captions altered.

On the price card, the field caption for the field, Metered Usage Price Limits is displayed as Metered Usage Levels.

The options in the picklist in ODTRM were:

- No Limits
- Metered Usage Limit 1
- Metered Usage Limit 2

In Microsoft Dynamics 365 Business Central - ODT Rentals, the options are:

- Unlimited
- 2 Levels
- 3 Levels

Therefore mapping is required for the options.

2 How to Setup Mapping on Metered Usage Level Field


The following displays the required mapping setup on the Rental Price table, field Metered Usage Price Limits.

Click on **Table ID = 70014203, Table Name = ODT Rental Price**


Table ID ↑	Table Name	Pa
70014203	ODT Rental Price	
70014245	ODT Rental Package Line	




Click on the navigation menu item popup **Table**




Click on the navigation menu item **Fields**



Click on the cell **Field Name** with the value **Metered Usage Price Limits**




Click on the navigation menu item **Mapping**






Click on the cell **Old Value**



Enter the text **Unlimited.**



Click on the cell **New Value**



Enter the text **No Limit.**





Click on the cell **Old Value**

S - RENTAL PR EDIT - CONFIG. FIELD MAPPING

Field ID Old Value ↑

138 → Unlimited

159

160

161

170

171

172

173

Enter the text **2 Levels**.

S - RENTAL PR EDIT - CONFIG. FIELD MAPPING

Field ID Old Value ↑

138

159 Unlimited

160 →

161

170

171

172

173

Click on the cell **New Value**

EDIT - CONFIG. FIELD MAPPING

New Value

No Limit

Enter the text **Metered Usage Limit 1.**

EDIT - CONFIG. FIELD MAPPING

New Value

No Limit

Metered Usage Limit 1.



Click on the cell **Old Value**

Field ID	Old Value ↑
158	Unlimited
159	→ 2 Levels
160	→
161	
170	
171	
172	
173	
174	

Enter the text **3 Levels**.

Field ID	Old Value ↑
158	Unlimited
159	2 Levels
160	→ 3
161	
170	
171	
172	
173	
174	

Click on the cell **New Value**

New Value
No Limit
Metered Usage Limit 1
→

Enter the text **Metered Usage Limit 2**.

New Value
No Limit
Metered Usage Limit 1
Metered Usage Limit 2
→



Click on the button **Close**

