



Woody in2it v2.7 Update instructions

The following procedure describes [Woody in2it](#) update from a previous version to version 2.7.

The new features, improvements and bug fixes are described in the corresponding release note.

Update procedure

1. Stop [Woody in2it](#) through the contextual menu of the Woody icon in the notification area (Windows systray).
2. Uninstall [Woody in2it](#) through Windows control panel.
3. Open Chromium web browser and purge cache (shortcut Ctrl+Shift+Del).
4. Rename the folder C:\ProgramData\Woody Technologies\Woody in2it, in case of rollback or to import profiles in the new version.
5. Install the new version of [Woody in2it](#).

Upgrade from version 2.5.58 and later

Ingest profiles are compatible and can be imported in [Woody in2it](#).

6. From the backup of the config folder (renamed at step n°4), copy all *.profile files to C:\ProgramData\Woody Technologies\Woody in2it\config.
7. At the first start of [Woody in2it](#), the browser opens on Profiles configuration tab. Click on the [Import profiles](#) button at the bottom of the page. Profiles are imported. By default, imported profiles are disabled. You can enable a profile by check in the [Active](#) box at the top of the page.
8. Configure general settings of [Woody in2it](#) in the setup tab, in particular the number of simultaneous ingest streams.
9. In the Manager tab, don't forget to start all the components by the [Start](#) button of the first line.

Upgrade from a version older than 2.5.58

Ingest profiles are not compatible for versions older than 2.5.58.

6. At the first start of [Woody in2it](#), the browser opens on Profiles configuration tab. Re-create yours ingest profiles. You can open old profiles files (previously backedup) with a text editor to copy and paste the fields values.

Note: Conditional transcoding rules have been changed since version 2.6. To get more details, please refer to the "Profiles configuration guide".

7. Configure general settings of [Woody in2it](#) in the setup tab, in particular the number of simultaneous ingest streams.
8. In the Manager tab, don't forget to start all the components by the [Start](#) button of the first line.

