



Woody Outgest

Update instructions

The following procedure describes [Woody Outgest](#) update from a previous version to version 2.8. The new features, improvements and bug fixes are described in the corresponding release note.

Note regarding installation on Windows 7 or Windows 2008 Server

In case of installation of version 2.8 on Windows 7 or Windows 2008 Server, an error message can appear when launching the installer.

If it happens, please install the required Windows KB as described in this procedure: <http://support.woody-technologies.com/solution/articles/24000013495-installation-of-64-bits-version-of-woody-products-causes-error-on-some-operating-systems>

Update procedure

1. Stop [Woody Outgest](#) service through the Windows console.
2. Uninstall [Woody Outgest](#) through Windows control panel.
3. Open your web browser and purge its cache (shortcut Ctrl+Shift+Del).
4. Rename the folder C:\ProgramData\Woody Technologies\Woody Outgest, in case of rollback or to import profiles in the new version.
5. Install the new version of [Woody Outgest](#).

Upgrade from version 2.6.x and later

Outgest profiles are compatible and can be imported in [Woody Outgest](#).

6. From the backup of the config folder (renamed at step n°4), copy all ***.profile** files and **profiles.wcfg** to C:\ProgramData\Woody Technologies\Woody Outgest\config.
7. From the backup of the config folder (renamed at step n°4), copy the ***.wcfg** files corresponding to your watchfolders in C:\ProgramData\Woody Technologies\Woody Outgest\config.
8. From the backup of the config folder (renamed at step no4), copy the whole **DataLog** folder to C:\ProgramData\Woody Technologies\Woody Outgest.
9. At the first start of [Woody Outgest](#), go to the Setup tab and click on the Import watchfolders button at the bottom of the page.
10. Configure general settings of [Woody Outgest](#) in the setup tab, in particular the number of simultaneous streams.
11. In the Manager tab, don't forget to start all the components by the Start button of the first line.

Upgrade from a version older than 2.6.x

Outgest profiles are not compatible for versions older than 2.6 .x

In case of upgrade from a previous version, profiles and watchfolders needs to be re-created after installation.

Do not hesitate to contact Woody Technologies support for any question or issue.