



Woody in2it essentials

Installation notes

1. Software installation

For software installation, please refer to the following guides:

Installation guide:

<http://support.woody-technologies.com/helpdesk/attachments/24048205858>

User Guide:

<http://support.woody-technologies.com/helpdesk/attachments/24048225334>

2. Software configuration


A specific configuration is required on Woody in2it essentials clients.

When you first open the **Woody in2it** application, the interface will ask you to enter your User Name and Password. Use default credentials

User name: administrator


Password: woody

In the setup page, you have to upload a license with “essentials” option.




The essentials option should appear on the license page.


Once the license uploaded, logout from the administration panel:

(Click on  button, on top right corner to log-out)

You can see that the login panel have changed.



Enter following information, then click **ADD** button.




Endpoint: The full URL of the server, have to be at the format:
https://server_ip:port

-User name: a user configured on the server.

-Password: the corresponding password for this user.


If you want to configure several servers, repeat this operation.

Your server will be added on the list.




You can now log in your in2it essentials, with any user account configured on the server.

Once logged-in, on the setup tab, you need to configure a shared storage path (UNC).



This storage location will be used to share media files and metadata between the client and server. This storage needs to be accessible by both server and client and must be an UNC path.

Save your configuration.

You can now navigate to the user interface (click on  button, on top right corner) and use your Woody in2it essentials client.