



## Woody in2it v2.6 Update instructions

The following procedure describes Woody in2it update from a previous version to version 2.6.

The new features, improvements and bug fixes are described in the corresponding release note.

### Update procedure

---

1. Stop Woody in2it through the contextual menu available on Woody in2it icon in the Windows notification area (system tray).
2. Uninstall Woody in2it through Windows control panel.
3. Open Chromium browser and purge cache (shortcut Ctrl+Alt+Del).
4. Backup the folder C:\ProgramData\Woody Technologies\Woody in2it\config in a different location, in case of rollback or to import profiles in the new version.
5. Delete the folder C:\ProgramData\Woody Technologies\Woody in2it\.
6. Install the new version of Woody in2it.

### Update from another 2.6.X version

Ingest profiles are compatible and can be imported in Woody in2it :

7. From the backup of the config folder (created at step no4), copy all \*.profile files to C:\ProgramData\Woody Technologies\Woody in2it\config.
8. At the first start of Woody in2it, the browser opens on Profiles configuration tab. Click on the « Import profiles » button at the bottom of the page. Profiles are imported. By default, imported profiles are disabled. You can enable a profile by checkin the « Active » box at the top of the page.
9. Configure general settings of Woody in2it in the setup tab, in particular the number of simultaneous ingest streams.
10. In the Manager tab, don't forget to start all the components by the « Start » button of the first line.

### Update from a version older than 2.6

Ingest profiles are not compatibles for versions older than 2.6.X.

7. At the first start of Woody in2it, the browser opens on Profiles configuration tab.. Re-create your ingest profiles. You can open old profiles files (previously backedup) with a text editor to copy and paste the fileds values.

Note : Conditionnal transcoding rules have been changed in version 2.6. To get more details, please refer to the « Profiles configuration guide».

8. Configure general settings of Woody in2it in the setup tab, in particular the number of simultaneous ingest streams.
9. In the Manager tab, don't forget to start all the components by the « Start » button of the first line.