



Installation Guide

iRise® Studio and iRise® Reader

iRise 8.9

Copyright © 2001-2012 iRise. All rights reserved.

The term "iRise" is a registered trademark of iRise in the U.S. and other countries.

Protected by one or more of the following US patents and their counterparts in other countries: 7,174,286, 7,349,837, 7,788,647 and 7,861,158. Other Patents Pending.

Portions of iRise products include software from:

John Resig, Copyright © 2009 John Resig, <http://jquery.com/>

Yahoo! Copyright © 2010, Yahoo! Inc. All rights reserved.

MetaStuff, Copyright © 2001-2005 MetaStuff, Ltd. All Rights Reserved. <http://www.dom4j.org>

OOS.ch, Copyright © 2004-2011 OOS.ch. All rights reserved.

INRIA, France Telecom, Copyright © 2000-2011 INRIA, France Telecom. All rights reserved.

JGoodies Karsten Lentzsch, Copyright © 2002-2009 JGoodies Karsten Lentzsch. All rights reserved.

The Indiana University Extreme! Lab Copyright © 2002 Extreme! Lab, Indiana University.
(<http://www.extreme.indiana.edu/>). All rights reserved.

Joe Walnes and XStream Committers, Copyright © 2003-2006, Joe Walnes Copyright © 2006-2007, XStream Committers.
All rights reserved.

Ivan Bozhanov, Copyright © 2010 Ivan Bozhanov (<http://vakata.com>)

Paul Bakaus, Copyright © 2010 Paul Bakaus, <http://jqueryui.com/>

The OpenSymphony Group (<http://www.opensymphony.com/>)

XMLmind Spell-Checker Copyright © 2002-2007 Pixware SARL

Brandon Aaron, Copyright © 2006 Brandon Aaron

Mika Tuupola, Copyright © 2007-2008 Mika Tuupola

Andris Valums, Copyright © 2008 Andris Valums, <http://valums.com>

Eric Garside, Copyright © 2009 Eric Garside (<http://eric.garside.name>)

Matt Kruse, Copyright © 2005-2009 Matt Kruse (<http://javascripttoolbox.com>)

Tuckey.org, Copyright © 2010 Tuckey.org. All Rights Reserved.

Klaus Hartl, Copyright © 2010 Klaus Hartl

Tim Down, Copyright © 2009 Tim Down

ESAPI, Copyright © 2007, The OWASP Foundation. All rights reserved.

Other brand and product names are trademarks or registered trademarks of the respective holders.

Table of Contents

| | |
|---|----|
| Installation Preparation | 5 |
| Components of iRise 8.9..... | 5 |
| iRise Studio..... | 5 |
| iRise Reader..... | 5 |
| iRise Definition Center | 5 |
| System Requirements..... | 6 |
| Studio Client Requirements..... | 6 |
| Reader Client Requirements..... | 8 |
| Downloading the Installer..... | 9 |
| Obtaining a License Key..... | 9 |
| Installing iRise Studio and iRise Reader | 10 |
| Installation Overview..... | 10 |
| Before You Install..... | 10 |
| Running the Installation..... | 10 |
| Previous Installations..... | 10 |
| Follow the Installer Steps..... | 11 |
| Uninstalling iRise Studio and iRise Reader..... | 14 |
| Troubleshooting | 15 |
| Resolving Issues..... | 15 |
| Memory Issues..... | 15 |
| iRise Studio Data Location..... | 16 |
| Appendix | 17 |
| Enabling SSL for the iRise Studio Client..... | 17 |
| Contact Us | 19 |

Installation Preparation

Components of iRise 8.9

iRise 8.9 is the latest generation of the award-winning iRise application simulation platform. iRise makes creating interactive, functionally rich simulations even faster and broadens the ways in which business and development stakeholders work together to quickly agree on what to build.

iRise has the following components:

iRise Studio

The iRise Studio client allows users to produce a robust, detailed application simulation and its associated requirements document. Studio can connect to Definition Center using standard *http* or *https* protocols, or can function in offline mode.

iRise Reader

The iRise Reader client allows users to review the interactive simulation and its associated requirements in a browser. The iRise Reader may be used to review projects on Definition Center. Projects exported to Interactive Document files (iDocs) can also be reviewed in Reader if you download the free iRise Reader software¹.

iRise Definition Center

iRise Definition Center allows users to share and collaborate on projects. Users can create, store and review projects simultaneously on a server that is accessible to all users. iRise Definition Center is installed separately.

¹ iRise Reader only needs to be installed to review iDocs. If reviewing projects on a Definition Center, then you do not need to install iRise Reader.

System Requirements

There are two client-side components installed as part of iRise suite: iRise Studio® client and iRise® Reader. Please review the relevant sections below to make sure the client machine meets the minimum requirements.²

Studio Client Requirements

iRise Studio allows you to create simulations and annotate them with requirements.

iRise Studio Hardware Requirements

Hardware requirements for running the iRise Studio client depend on the usage patterns of the user. In general, the iRise Studio client will run faster with (in this order of effectiveness beyond the Minimum Requirements):

- System RAM (up to 1.5GB of available physical memory can be utilized)
- Number of CPU's - iRise software is multi-threaded and will utilize multiple CPU's
- Faster CPU's
- Faster hard drive speed

| Item | Minimum Requirement |
|------------------------|--|
| CPU | 1 GHz Pentium® IV (or equivalent) |
| System RAM | 512MB (1GB recommended) 4GB for Mac® running virtual windows (32 bit) |
| Hard Drive | 500MB (1GB recommended) |
| Network Interface Card | 100MB/Second Ethernet |

² iRise Studio will not connect to iRise Definition Center unless both are running the same major-minor version, e.g. 8.9.x. Contact your iRise administrator to determine whether your Definition Center has been upgraded.

iRise Studio Software Requirements

| Item | Minimum Requirement |
|-------------------|--|
| Web Browser | Microsoft® Internet Explorer v7.0 Microsoft® Internet Explorer v8.0 Mozilla® Firefox v3.5 Apple® Safari v4 (Windows) Apple® Safari v5 (Mac) Google® Chrome v8 (Windows) Google® Chrome v10 (Mac) |
| Operating Systems | Microsoft® Windows 7* Microsoft® Vista* SP2 Microsoft® XP* SP3 Microsoft® Windows Server 2008* R2 Microsoft® Windows Server 2003* SP2 Mac-Windows emulator® using Windows OS (VMware Fusion or Parallels Desktop) Mac OS X 10.6 (Snow Leopard) Mac OS X 10.7 (Lion) *iRise Studio is a 32 bit application but will run on 64 bit |
| Network Protocol | Microsoft® TCP/IP |

Reader Client Requirements

Installing iRise Reader allows you to open and review iDocs.

iRise Reader Client Hardware Requirements

| Item | Minimum Requirement |
|------------------------|---|
| CPU | 1 GHz Pentium® IV (or equivalent) |
| System RAM | 512MB 2GB for Mac® running virtual Windows® (32 bit) |
| Hard Drive | 200MB (300 MB recommended) |
| Network Interface Card | 100MB/Second Ethernet |

iRise Reader Client Software Requirements

| Item | Minimum Requirement |
|-------------------|---|
| Browser | Microsoft® Internet Explorer v7.0 Microsoft® Internet Explorer v8.0 Mozilla® Firefox v3.5 Apple® Safari v4 (Windows) Apple® Safari v5 (Mac) Google® Chrome v8 (Windows) Google® Chrome v10 (Mac) |
| Operating Systems | Microsoft® Windows 7 Microsoft® Vista SP2 Microsoft® XP SP3 Microsoft® Windows Server 2008 R2 Microsoft® Windows Server 2003 SP2 MAC-Windows emulator® using Windows OS (VMware Fusion or Parallels Desktop) Mac OS X 10.6 (Snow Leopard) Mac OS X 10.7 (Lion) |
| Network Protocol | Microsoft® TCP/IP |

Downloading the Installer

iRise Studio and iRise Reader share a single installer. The installer is available for download on the iRise secure customer site:

<https://irise.subscribenet.com>

Note: iRise® will provide you with a username and password to log in to the secure customer site.

The installer is a self-extracting executable that can be run directly from the secure customer site. The executable can also be saved to a local drive.

Note: The iRise Reader can also be downloaded separately by those users who want to view iDoc files. Please go to <http://www.irise.com> for more details.

Obtaining a License Key

To run iRise Studio, you need a valid Studio license key. If you already have a valid license for iRise 5 or iRise 6, then you need not download a new license for iRise 8.9. If you do need a license, they are available for download on the protected customer site at the following Internet address: <https://irise.subscribenet.com>

Note: iRise® will provide you a customer-specific username and password for login to the URL.

To download the Studio license key:

- 1 Go to: <http://irise.subscribenet.com> and log in.
- 2 Select the Click here to download a License Key link to the right of the appropriate iRise product in the Product List.
- 3 Follow the onscreen instructions to download the license.

To generate the License Key, you must enter the physical MAC Address of the client machine.

The physical address of the server computer can be identified by typing `ipconfig/all` from a command prompt. If the client machine has multiple physical addresses, include them all.

Note: Always follow the instructions above to download a license key. Clicking the License Keys menu option on the Product Download page can prevent you from accessing the full set of entitlements available to you for that product.

Installing iRise Studio and iRise Reader

Installation Overview

iRise Studio and iRise Reader clients share an installer. The iRise Reader is automatically installed with iRise Studio and it is a required component.

Before You Install

Before you install iRise Studio, verify the following:

- 1 There is at least 300MB of hard disk space is available to temporarily extract and then install the selected components to the following directory:
C:\Documents and Settings\machinename\Local Settings\Temp
If 300MB is not available in the above destination, you must either:
 - Free up disk space ; OR
 - Reset the Windows Temp System Environment variable to a destination that has at least 300MB hard disk space available.
- 2 You have sufficient Windows permissions to install new software on the client computer.
- 3 You have full access (read and write) to the installation directory (default c:\Program Files\iRise) to run iRise Studio or iRise Reader.

Please contact your local system administrator to verify your Windows permissions allow you to add new software to the client computer and run the software after it is installed.

Note to McAfee VirusScan users: Do not disable McAfee VirusScan to perform the installation or you may encounter installation issues.

Running the Installation

Previous Installations


iRise 8.9 cannot be installed in parallel to previous installations. When you start iRise 8.9 for the first time, Studio will automatically convert your private projects to iRise 8.9 format. This will cause a onetime delay the first time you start iRise Studio. When you open an iDoc created with a version prior to iRise 8.9, the iDoc will be converted to iRise 8.9 format. Save a backup of the iDoc before you open it in Reader to avoid this.

Follow the Installer Steps

To install iRise Studio and iRise Reader:


- 1 Launch the installer executable by double-clicking the file you downloaded. The executable will automatically extract the Installer to a temporary directory on the client machine.
- 2 The InstallShield Installer Wizard launches. Follow the InstallShield installation screens.

Screen 1: This is the Introduction Screen. Click Next to start the installation.




Screen 1: Introduction Screen

Screen 2: Select the install destination directory for the software, then click Next.




Screen 2: Choose Install Folder

Screen 3: If you have data from previous Studio installations (i.e., local or private projects), then all projects that you have checked out from the Definition Center must be checked back into the Definition Center before continuing. If this is the case, cancel the installation and check the projects back into the Definition Center. If you do not have any projects checked out, then click Next.




Screen 3: Detected Data

Screen 4: This screen summarizes the details of the installation that is about to take place. Click Next.




Screen 4: Pre-Installation Summary

Screens 5-6: When the installation is complete. Click Done and continue with license download instructions.



Screen 5: Installing ...



Screen 6: Install Complete

Uninstalling iRise Studio and iRise Reader

To uninstall iRise Studio:

- 1** From the Windows Control Panel, select Add or Remove Programs.
- 2** Locate iRise Studio on the list of programs, and then click the Change/Remove button. The iRise Studio Uninstaller Screen appears.
- 3** Follow the onscreen steps.

Note: You will have the option of uninstalling iRise Reader when you uninstall iRise Studio.

Troubleshooting

Resolving Issues

The following section addresses common issues that may arise during either the installation or usage of the iRise product suite. If you continue to encounter problems after reviewing the recommendations in this section, please refer to the Contact Us section at the end of this document for information about contacting iRise Customer Support. The [iRise Support Knowledgebase](#) is also an excellent source of technical information for troubleshooting installation or configuration issues.

Memory Issues

Performance and stability of the iRise Studio client may be affected by available memory in the client machine.

The following memory-related issues may arise if the minimum System Requirements for memory are not met in the client machine:

- If the client machine RAM is completely utilized, iRise Studio will begin to use Virtual Memory (the swap file). Application performance could be greatly impaired as a result.
- If both the RAM and the Virtual Memory approaching the maximum size, iRise Studio may become unstable.

Note: To ensure optimal performance if iRise Studio and the iRise Definition Center are running on the same machine, the machine must meet the *total minimum System Requirements for both components*.

If the recommended System Requirements have been met and memory resource issues persist, please contact iRise Customer Support.

To make more memory available on the client:

- 1 Close all other applications that are running.
- 2 Use the Windows Task Manager to close background applications and services .

iRise Studio Data Location

The iRise Studio stores data for “private” projects on your computer.

If iRise Studio 8.9 is the first version of iRise Studio to be installed on your computer (i.e., you are not upgrading to 8.9), then by default your data will be stored at C:\Users\[username]\iRise\Studio\data on Windows Vista/7 machines and C:\Documents and Settings\[username]\iRise\Studio\Data on Windows XP machines.

If you are upgrading to 8.9, and you have Windows XP installed, the data will stay in its current location (default C:\Program Files\iRise\Studio\data).

If you are upgrading from a version prior to 7.2 on a Windows Vista machine, then iRise Studio will prompt you to copy the data from C:\Program Files\iRise\Studio\data to C:\Users\[username]\iRise\Studio\Data when you start iRise Studio for the first time.

Enabling SSL for the iRise Studio Client

There are two scenarios for using certificates to enable SSL communication:

Scenario I: Using a digital certificate that uses a trusted certificate authority (CA) as the root certificate authority, such as VeriSign. No further steps are needed.

Scenario II: Using a digital certificate that uses a non-trusted CA, such as Microsoft® Certificate server, as the root certificate authority. For example, a digital certificate could be generated from your organization's local certificate server. A locally-generated root certificate would then need to be present in the CACERTS file of the iRise Studio client. CACERTS is a file used to keep the root certificates of signing authorities. There are two options to ensure the root certificate is present in this CACERTS file:

First option: If you already have a CACERTS file with the root certificate present, you can make a copy and save it on for the iRise Studio client. The following steps describe how to do this:

- a. Locate an existing CACERTS file that has the internal root CA server added to it. This could be from the server as described above, in Enabling HTTPS.
- b. Copy this CACERTS file to the `.._jvm\lib\security` folder of the iRise Studio client. The default location of the CACERTS file for iRise Studio is `C:\Program Files\iRise\Studio_jvm\lib\security`.

Second option: add a root certificate authority manually using the steps below.

1. Get a root certificate

If you have not already done so, you will need to get a root certificate from the non-trusted CA. For example, if you have an internal certificate server, such as Microsoft® Certificate server, then you would download the root certificate and save it to `C:\Program Files\iRise\Studio_jvm\lib\security`. For the purposes of the following steps, the root certificate will be referred to as `rootcert.cer`. We recommend that you save the file as `rootcert.cer`.

2. Import the root certificate into CACERTS

- a. Open a command-line prompt (Start | Run... | `cmd`) and change the drive letter to C: (or the drive location of the iRise Studio client, if not the C: drive).

- b. Change directory to the ..._jvm\lib\security folder of the iRise Studio client:
`>cd ^"Program Files\iRise\Studio_jvm\lib\security"`
- c. Ensure that the CA root certificate is present in this directory. For example, if you named it rootcert.cer:
`>dir rootcert.cer`
If it says "File Not Found" then go back to step 1 and save the rootcert.cer file in the appropriate location (i.e., C:\Program Files\iRise\Studio_jvm\lib\security).
- d. Ensure that the CACERTS file is also present in this directory:
`>dir CACERTS`
If it says "File Not Found" then you probably have to copy another CACERTS from another location.
- e. A Java utility called keytool.exe allows you to import root certificates into the CACERTS file. If the Java bin directory is in your path, you can run keytool.exe from any path location open in the command-prompt. However, since there could be different Java installations on your machine from various applications, we recommend that you run keytool.exe exactly as indicated here:

```
> C:\Program Files\iRise\Studio\_jvm\lib\security\keytool -import -file rootcert.cer -alias rootCA -keystore cacerts
```

You should include the full path of keytool.exe as shown above, but be sure the path corresponds to your iRise Studio installation.

Note that *rootCA* is the name of the root certificate server from which rootcert.cer was downloaded. This is the fully qualified name of the CA Root server or the internal machine name in the domain.

- f. When prompted to do so, enter the password to the CACERTS keystore (default is changeit)
- g. Answer yes when prompted on the command line.

If you indicated that SSL would be used during installation, then the iRise Studio client is now ready to be used with SSL.

Contact Us

iRise Customer Support is open Monday through Friday (except for holidays).

Toll Free: (866) 361-3900

E-mail: support@irise.com

Internet: <http://www.irise.com/support>

iRise Customer Support may redirect inquiries regarding Professional Services, Training, or Sales questions.