


Stealth Button Guide
(in programming mode)



The Blendtec Stealth incorporates the latest technology available in today’s commercial blenders—not the least of which is the state-of-the-art control surface that allows you to manage and fine-tune your blender’s programming.

Selecting a Profile

- To select a profile, follow the steps below:
- Enter programming mode by touching and holding (X) for 3 seconds.
 - Touch (checkmark) to select Profiles.
 - To choose 1 of the standard profiles preprogrammed on the machine, select Standard Profiles by touching (checkmark).
 - To choose a custom profile designed via the Blend Wizard, touch (down arrow) to scroll to Custom Profiles and then touch (checkmark).
 - After selecting the standard or custom profile category, touch (down arrow) to scroll through the profiles in the category, and touch (checkmark) to select the desired profile.
 - The LED screen will list the selected profile and the question “Make this the active profile?” Touch (checkmark) to load the blender with the profile, or touch (X) to cancel and return to the previous menu.

Changing the Programmed Cycle Buttons

- After loading the desired profile, complete the following steps to change 1 of the blend cycles in the profile:
- Enter programming mode by touching and holding (X) for 3 seconds.
 - Touch (down arrow) to scroll to the second menu item (Blend Cycles), and then touch (checkmark).
 - Select the first or second option. The first option (Standard Blend Cycles) lists the cycles preprogrammed on the blender. The second option (Custom Blend Cycles) lists the custom cycles that can be designed via the Blend Wizard and exported to the blender. Select the first or second option by touching (checkmark).

- Touch (down arrow) to scroll to the desired cycle, and then touch (checkmark).
- The LED screen will then prompt you to choose which number on the control surface you want to assign the cycle to. Touch the number, and then touch (checkmark) to program the button with the selected cycle.

Creating Profiles and Cycles via the Blend Wizard™

In addition to using the profiles and cycles preprogrammed on your blender, you can use the Blend Wizard to create custom profiles that include current Blendtec cycles and/or custom cycles. For instructions on using the Blend Wizard to easily develop custom profiles and cycles, visit blendtec.com/commercial/program.

Importing Custom Profiles and Cycles to the Blender

- Once you have completed the Blend Wizard instructions and transferred a custom profile file to a USB flash drive, follow the steps below to import the file to the blender.
- Use a Phillips screwdriver to remove the USB cover at the top of the right side of the blender.
 - Insert the USB flash drive into the blender’s USB port.
 - If the blender is in manual or automatic operation mode, the USB drive menu will automatically load on the LED screen. If the LED screen is already in programming mode, go to the main menu, touch (down arrow) to scroll to menu item 5 (USB Flash Drive), and then touch (checkmark).
 - From the USB flash drive menu, touch (checkmark) to select option 1 (Import Profile).
 - Touch (down arrow) to scroll through the items on the flash drive and locate the desired custom profile file (by default named stealth.bpf). (Note: Items with a + sign next to them are folders; if the custome profile file is in a folder, touch (checkmark) to open the folder and see the files in the folder.) Select the desired file by touching (checkmark).
 - Touch (checkmark) to start the import process. After the file has been imported, the custom profile will be automatically loaded as the active profile on the blender.
 - Remove the USB drive from the blender, and secure the USB cover on the USB port with a Phillips Screwdriver.

For detailed operation instructions, refer to Section 5 of the Stealth Owner’s manual.


Preloaded Blending Profiles

Smoothie Profile			Multipurpose Profile		
1		20 seconds	1		18 seconds
Small Smoothie with Fresh Fruit			Small Milkshake		
2		25 seconds	2		14 seconds
Medium Smoothie 4			Granita / Medium Milkshake		
3		14 seconds	3		14 seconds
Granita / Medium Milkshake			Small Margarita / Ice Cappuccino		
4		23 seconds	4		25 seconds
Medium Smoothie 3			Medium Smoothie 4		
5		40 seconds	5		40 seconds
Large Smoothie 4			Large Smoothie 4		
6		50 seconds	6		50 seconds
50 Seconds at Speed 7			50 Seconds at Speed 7		
		Pulse			Pulse
Pulse at Speed 7			Pulse at Speed 7		
Coffee Profile			Milkshake Profile		
1		14 seconds	1		18 seconds
Small Margarita / Ice Cappuccino			Small Milkshake		
2		20 seconds	2		14 seconds
Large Ice Cappuccino			Granita / Medium Milkshake		
3		12 seconds	3		18 seconds
Small Slushy / Milkshake			Milkshake with Frozen Fruit		
4		14 seconds	4		24 seconds
Granita / Medium Milkshake			Large Milkshake 1		
5		32 seconds	5		27 seconds
Large Smoothie 2			Large Milkshake 2		
6		50 seconds	6		35 seconds
50 Seconds at Speed 7			Large Milkshake 3		
		Pulse			Pulse
Pulse at Speed 7			Pulse at Speed 7		

Blend Cycle Library

The Stealth's preprogrammed blend cycles will handle nearly every blending need—from milkshakes to margaritas to the smoothest of smoothies.

1		7 seconds	15		35 seconds
2		23 seconds	16		20 seconds
3		50 seconds	17		19 seconds
4		90 seconds	18		23 seconds
5		45 seconds	19		23 seconds
6		14 seconds	20		25 seconds
7		20 seconds	21		28 seconds
8		35 seconds	22		32 seconds
9		12 seconds	23		36 seconds
10		18 seconds	24		40 seconds
11		14 seconds	25		50 seconds
12		18 seconds	26		40 seconds
13		24 seconds	27		32 seconds
14		27 seconds	28		59 seconds

29		67 seconds	37		Pulse
30		23 seconds	38		Pulse
31		50 seconds	39		Pulse
32		50 seconds	40		Pulse
33		50 seconds	41		Pulse
34		50 seconds	42		Pulse
35		50 seconds	43		Disabled
36		50 seconds			

Blend Wizard™ Web App

Log in to blendtec.com/commercial/program to download even more from our vast library of blend cycles, alter cycles to meet your specific needs, or even create your own cycles from scratch!



Blendtec
COMMERCIAL



Stealth™
Blend Cycle Reference Guide